

Package ‘otelsdk’

September 10, 2025

Title 'R' 'SDK' and Exporters for 'OpenTelemetry'

Version 0.2.0

Description 'OpenTelemetry' is a collection of tools, 'APIs', and 'SDKs' used to instrument, generate, collect, and export telemetry data (metrics, logs, and traces) for analysis in order to understand your software's performance and behavior. This package contains the 'OpenTelemetry' 'SDK', and exporters. Use this package to export traces, metrics, logs from instrumented 'R' code. Use the 'otel' package to instrument your 'R' code for 'OpenTelemetry'.

License MIT + file LICENSE

Encoding UTF-8

RoxygenNote 7.3.2.9000

SystemRequirements cmake, protobuf-compiler, libprotobuf, libcurl, zlib, GNU make

Imports otel, utils

Suggests callr, cli, curl, gh, jsonlite, processx, ps, rlang, spelling, testthat (>= 3.0.0), webfakes, withr

Config/testthat/edition 3

URL <https://otelsdk.r-lib.org>, <https://github.com/r-lib/otelsdk>

Config/Needs/check r-lib/otel, gaborcsardi/testthatlabs

Config/Needs/coverage r-lib/otel, gaborcsardi/testthatlabs

Config/Needs/website tidyverse/tidytemplate, r-lib/otel

BugReports <https://github.com/r-lib/otelsdk/issues>

NeedsCompilation yes

Author Gábor Csárdi [aut, cre],
Posit Software, PBC [cph, fnd] (ROR: <<https://ror.org/03wc8by49>>),
opentelemetry-cpp authors [ctb]

Maintainer Gábor Csárdi <csardi.gabor@gmail.com>

Repository CRAN

Date/Publication 2025-09-10 08:00:06 UTC

Contents

Collecting Telemetry Data	2
Environment Variables	5
File Size Options	12
logger_provider_file	12
logger_provider_http	14
logger_provider_stdstream	19
meter_provider_file	20
meter_provider_http	22
meter_provider_memory	27
meter_provider_stdstream	28
Time Interval Options	29
tracer_provider_file	30
tracer_provider_http	32
tracer_provider_memory	37
tracer_provider_stdstream	38
with_otel_record	39
Index	41

Collecting Telemetry Data

Collecting Telemetry Data

Description

This page is about collecting telemetry data from instrumented R packages. If you need help with instrumenting your R package, see [Getting Started](#) in the otel package.

Value

Not applicable.

Usage

- Instrument your R package or project using the [otel](#) package. Alternatively, use [Zero Code Instrumentation](#) to automatically instrument selected packages.
- Install the otelsdk package.
- Choose an exporter from the otelsdk package. The http exporter sends OpenTelemetry output through OTLP/HTTP.
- Set the OTEL_TRACES_EXPORTER environment variable to point to the exporter of your choice. E.g. for OTLP/HTTP set OTEL_TRACES_EXPORTER=http.
- If you are sending telemetry data through HTTP, then you typically need to configure the URL of your OpenTelemetry collector, and you possibly also need to supply a token in an HTTP header, possibly some resource attributes. Follow the instructions of the provider of your collector. They typically don't have instructions for R, but generic instructions about environment variables will work for the otelsdk R package. E.g. for [Grafana](#) you need something like

```

OTEL_EXPORTER_OTLP_PROTOCOL="http"
OTEL_EXPORTER_OTLP_ENDPOINT="https://otlp-gateway-prod-eu-central-0.grafana.net/otlp" \
OTEL_RESOURCE_ATTRIBUTES="service.name=<name-of-your-app>,service.namespace=<name-of-your-namespa
OTEL_EXPORTER_OTLP_HEADERS="Authorization=Basic%20<base64-encoded-token>"

```

See more examples below.

- See all [environment variables](#) and the manual of your chosen provider for details on configuring otelsdk exporters.
- Start R and your app. Telemetry data will be exported to the chosen exporter.

Setup

Setup for remote collectors:

There are a lot of services that offer an OpenTelemetry collector for tracers, logs and metrics, many of them supporting all three of them. There are also local apps that work as a collector. We tried otelsdk with the following ones:

Grafana:

Follow the [documentation](#). Create an API token. You'll need to use the Grafana instance ID as your username, and the token as the password in HTTP Basic auth. E.g. in R do this to get the base64 encoded token. `instance-id` is a (currently seven digit) number and a string with a `glc_` prefix.

```
openssl::base64_encode("<instance-id>:<api-token>")
```

Then use this encoded token to set the Authorization header:

```

OTEL_EXPORTER_OTLP_PROTOCOL="http"
OTEL_EXPORTER_OTLP_ENDPOINT="https://otlp-gateway-prod-eu-central-0.grafana.net/otlp" \
OTEL_EXPORTER_OTLP_HEADERS="Authorization=Basic%20<base64-encoded-token>"
OTEL_RESOURCE_ATTRIBUTES="service.name=<name-of-your-app>,service.namespace=<name-of-your-namespa

```

Your endpoint URL is probably different, use the one that you see on your dashboard.

If you want to export logs and/or metrics, set these environment variables, respectively:

```

OTEL_LOGS_EXPORTER=http
OTEL_LOG_LEVEL=debug
OTEL_METRICS_EXPORTER=http

```

It also makes sense to set the desired log level.

Grafana suggests running an OpenTelemetry collector on premise instead of sending telemetry data to them directly. But nevertheless you can start out without running your own collector, they call this "quick start" mode.

Pydantic Logfire:

Create a project and a write token. Note that the URLs you need to use are different if you are within the EU! You probably need to replace `us` with `eu` in the URL if you are in the EU. Set these environment variables:

```

OTEL_TRACES_EXPORTER=http
OTEL_EXPORTER_OTLP_ENDPOINT="https://logfire-us.pydantic.dev"
OTEL_EXPORTER_OTLP_HEADERS="Authorization=<your-write-token>"

```

For logs also set `OTEL_LOGS_EXPORTER` and the desired log level:

```

OTEL_LOGS_EXPORTER=http
OTEL_LOG_LEVEL=debug

```

For exporting metrics also set
`OTEL_METRICS_EXPORTER=http`

Setup for local collectors:

otel-tui:

`otel-tui` is a terminal app that supports traces, logs and metrics. It is great for development, as you can keep all your telemetry local while instrumenting your package or app. Follow the installation instructions and then run the app from a terminal:

```
otel-tui
```

It listens on the default port, so the setup is very simple, set these environment variables (or a subset if you don't want metrics or logs):

```
OTEL_TRACES_EXPORTER=http
OTEL_LOGS_EXPORTER=http
OTEL_LOG_LEVEL=debug
OTEL_METRICS_EXPORTER=http
```

otel-desktop-viewer:

`otel-desktop-viewer` is similar to `otel-tui`, but has a web UI. Follow the installation instructions and start the app from a terminal:

```
otel-desktop-viewer
```

It should start a new windows or tab in your local web browser. Set the usual environment variable for your R app:

```
OTEL_TRACES_EXPORTER=http
```

Jaeger:

If you have Docker, you can start a **Jaeger** container on the default port:

```
docker run --rm --name jaeger \
  -p 16686:16686 \
  -p 4317:4317 \
  -p 4318:4318 \
  -p 5778:5778 \
  -p 9411:9411 \
  jaegertracing/jaeger:2.4.0
```

Go to `http://localhost:16686/` to view the Jaeger UI.

SigNoz:

To run SigNoz locally with Docker, clone the repository at <https://github.com/SigNoz/signoz>:

```
git clone --depth 1 https://github.com/SigNoz/signoz
```

and then run Docker Compose from the `deploy/docker/` subdirectory:

```
cd deploy/docker
docker compose up
```

Go to `http://localhost:8080` to see the SigNoz UI.

Examples

See above

Environment Variables *Environment variables to configure otelsdk*

Description

See also the [Environment Variables](#) in the otel package, which is charge of selecting the exporters to use.

Value

Not applicable.

The OpenTelemetry Specification

Most of these environment variables are based on the [OpenTelemetry Specification](#), version 1.48.0. The environment variables with an 'OTEL_R_' prefix are not (yet) in the standard, and are specific for the otel and otelsdk R packages.

General SDK Configuration

- OTEL_SDK_DISABLED
Set to a 'true' value to disable the SDK for all signals.
- OTEL_RESOURCE_ATTRIBUTES
Key-value pairs to be used as resource attributes. See the [Resource SDK](#) for more details.
- OTEL_SERVICE_NAME
Sets the value of the [service.name](#) resource attribute.
- OTEL_LOG_LEVEL
Log level used by the [SDK internal logger](#). In R it is also used for the default log level of the OpenTelemetry loggers.

Selecting Exporters

otel is responsible for selecting the providers to use for traces, logs and metrics. You can use the environment variables below to point the otel functions to the desired providers.

If none of these environment variables are set, then otel will not emit any telemetry data.

- OTEL_TRACES_EXPORTER
The name of the selected tracer provider. See [otel::get_default_tracer_provider\(\)](#) for the possible values.
- OTEL_R_TRACES_EXPORTER
R specific version of OTEL_TRACES_EXPORTER.
- OTEL_LOGS_EXPORTER
The name of the selected logger provider. See [otel::get_default_logger_provider\(\)](#) for the possible values.

- `OTEL_R_LOGS_EXPORTER`
R specific version of `OTEL_LOGS_EXPORTER`.
- `OTEL_METRICS_EXPORTER`
The name of the selected meter provider. See `otel::get_default_meter_provider()` for the possible values.
- `OTEL_R_METRICS_EXPORTER`
R specific version of `OTEL_METRICS_EXPORTER`.

Suppressing Instrumentation Scopes (R Packages)

`otel` has two environment variables to fine tune which instrumentation scopes (i.e. R packages, typically) emit telemetry data. By default, i.e. if neither of these are set, all packages emit telemetry data.

- `OTEL_R_EMIT_SCOPES`
Set this environment variable to a comma separated string of instrumentation scope names or R package names to restrict telemetry to these packages only. The name of the instrumentation scope is the same as the name of the tracer, logger or meter, see `otel::default_tracer_name()`. You can mix package names and instrumentation scope names and you can also use wildcards (globbing). For example the value
`OTEL_R_EMIT_SCOPES="org.r-lib.*,dplyr"`
selects all packages with an instrumentation scope that starts with `org.r-lib.` and also `dplyr`.
- `OTEL_R_SUPPRESS_SCOPES`
Set this environment variable to a comma separated string of instrumentation scope names or R package names to suppress telemetry data from these packages. The name of the instrumentation scope is the same as the name of the tracer, logger or meter, see `otel::default_tracer_name()`. You can mix package names and instrumentation scope names and you can also use wildcards (globbing). For example the value
`OTEL_R_SUPPRESS_SCOPES="org.r-lib.*,dplyr"`
excludes packages with an instrumentation scope that starts with `org.r-lib.` and also `dplyr`.

Zero Code Instrumentation

`otel` can instrument R packages for OpenTelemetry data collection without changing their source code. This relies on changing the code of the R functions manually using `base::trace()` and can be configured using environment variables.

- `OTEL_R_INSTRUMENT_PKGS`
Set `OTEL_R_INSTRUMENT_PKGS` to a comma separated list of packages to instrument. The automatic instrumentation happens when the `otel` package is loaded, so in general it is best to set this environment variable before loading R.
- `OTEL_R_INSTRUMENT_PKGS_<pkg>_INCLUDE`
For an automatically instrumented package, set this environment variable to only instrument a subset of its functions. It is parsed as a comma separated string of function names, which may also include `?` and `*` wildcards (globbing).

- `OTEL_R_INSTRUMENT_PKGS_<pkg>_EXCLUDE`
For an automatically instrumented package, set this environment variable to exclude some functions from instrumentation. It has the same syntax as its `*_INCLUDE` pair. If both are set, then inclusion is applied and the exclusion.

Attribute Limits

- `OTEL_ATTRIBUTE_COUNT_LIMIT`
Set this environment variable to limit the number of attributes for a single span, log record, metric measurement, etc. If unset, the default limit is 128 attributes. Note that only attributes specified with `otel::as_attributes()` are subject to this environment variable.
- `OTEL_ATTRIBUTE_VALUE_LENGTH_LIMIT`
Set this environment variable to limit the length of vectors in attributes for a single span, log record, metric measurement, etc. If unset, there is no limit on the lengths of vectors in attributes. Note that only attributes specified with `otel::as_attributes()` are subject to this environment variable.

OTLP/HTTP Exporters

These environment variables are used by [tracer_provider_http](#), [meter_provider_http](#) and [logger_provider_http](#).

For every set of environment variables, the signal specific ones have priority over the generic one.

- `OTEL_EXPORTER_OTLP_ENDPOINT` | `OTEL_EXPORTER_OTLP_TRACES_ENDPOINT` | `OTEL_EXPORTER_OTLP_METRICS_ENDPOINT` | `OTEL_EXPORTER_OTLP_LOGS_ENDPOINT`
OTLP URL to send telemetry data to. When the generic environment variable is used, the exporter appends the signal specific endpoint to it. The signal specific environment variables are used as is. More in the [OpenTelemetry specification](#).
- `OTEL_EXPORTER_OTLP_PROTOCOL` | `OTEL_EXPORTER_OTLP_TRACES_PROTOCOL` | `OTEL_EXPORTER_OTLP_METRICS_PROTOCOL` | `OTEL_EXPORTER_OTLP_LOGS_PROTOCOL`
The transport protocol. Possible values: `http/json`, `http/protobuf`.
- `OTEL_R_EXPORTER_OTLP_JSON_BYTES_MAPPING` | `OTEL_R_EXPORTER_OTLP_TRACES_JSON_BYTES_MAPPING` | `OTEL_R_EXPORTER_OTLP_METRICS_JSON_BYTES_MAPPING` | `OTEL_R_EXPORTER_OTLP_LOGS_JSON_BYTES_MAPPING`
Encoding used for trace ids and spans id. Possible values: `hexid`, `base64`, `hex`.
- `OTEL_R_EXPORTER_OTLP_USE_JSON_NAME` | `OTEL_R_EXPORTER_OTLP_TRACES_USE_JSON_NAME` | `OTEL_R_EXPORTER_OTLP_METRICS_USE_JSON_NAME` | `OTEL_R_EXPORTER_OTLP_LOGS_USE_JSON_NAME`
Whether to use json name of protobuf field to set the key of json. A boolean value (flag, true or false).
- `OTEL_R_EXPORTER_OTLP_CONSOLE_DEBUG` | `OTEL_R_EXPORTER_OTLP_TRACES_CONSOLE_DEBUG` | `OTEL_R_EXPORTER_OTLP_METRICS_CONSOLE_DEBUG` | `OTEL_R_EXPORTER_OTLP_LOGS_CONSOLE_DEBUG`
Whether to print debug messages to the console. A boolean value (flag, true or false).
- `OTEL_EXPORTER_OTLP_TIMEOUT` | `OTEL_EXPORTER_OTLP_TRACES_TIMEOUT` | `OTEL_EXPORTER_OTLP_METRICS_TIMEOUT` | `OTEL_EXPORTER_OTLP_LOGS_TIMEOUT`
HTTP timeout in milliseconds.
- `OTEL_EXPORTER_OTLP_HEADERS` | `OTEL_EXPORTER_OTLP_TRACES_HEADERS` | `OTEL_EXPORTER_OTLP_METRICS_HEADERS` | `OTEL_EXPORTER_OTLP_LOGS_HEADERS`
Additional HTTP headers to send. E.g. Authorization is commonly used. It must be a comma separated list of headers, each in the header=value form.

- `OTEL_R_EXPORTER_OTLP_SSL_INSECURE_SKIP_VERIFY` | `OTEL_R_EXPORTER_OTLP_TRACES_SSL_INSECURE_SKIP_VERIFY` | `OTEL_R_EXPORTER_OTLP_METRICS_SSL_INSECURE_SKIP_VERIFY` | `OTEL_R_EXPORTER_OTLP_LOGS_SSL_INSECURE_SKIP_VERIFY`
Whether to disable SSL. A boolean value (flag, true or false).
- `OTEL_EXPORTER_OTLP_CERTIFICATE` | `OTEL_EXPORTER_OTLP_TRACES_CERTIFICATE` | `OTEL_EXPORTER_OTLP_METRICS_CERTIFICATE` | `OTEL_EXPORTER_OTLP_LOGS_CERTIFICATE`
CA certificate, path to a file.
- `OTEL_EXPORTER_OTLP_CERTIFICATE_STRING` | `OTEL_EXPORTER_OTLP_TRACES_CERTIFICATE_STRING` | `OTEL_EXPORTER_OTLP_METRICS_CERTIFICATE_STRING` | `OTEL_EXPORTER_OTLP_LOGS_CERTIFICATE_STRING`
CA certificate, as a string.
- `OTEL_EXPORTER_OTLP_CLIENT_KEY` | `OTEL_EXPORTER_OTLP_TRACES_CLIENT_KEY` | `OTEL_EXPORTER_OTLP_METRICS_CLIENT_KEY` | `OTEL_EXPORTER_OTLP_LOGS_CLIENT_KEY`
SSL client key, path to a file.
- `OTEL_EXPORTER_OTLP_CLIENT_KEY_STRING` | `OTEL_EXPORTER_OTLP_TRACES_CLIENT_KEY_STRING` | `OTEL_EXPORTER_OTLP_METRICS_CLIENT_KEY_STRING` | `OTEL_EXPORTER_OTLP_LOGS_CLIENT_KEY_STRING`
SSL client key as a string.
- `OTEL_EXPORTER_OTLP_CLIENT_CERTIFICATE` | `OTEL_EXPORTER_OTLP_TRACES_CLIENT_CERTIFICATE` | `OTEL_EXPORTER_OTLP_METRICS_CLIENT_CERTIFICATE` | `OTEL_EXPORTER_OTLP_LOGS_CLIENT_CERTIFICATE`
SSL client certificate, path to a file.
- `OTEL_EXPORTER_OTLP_CLIENT_CERTIFICATE_STRING` | `OTEL_EXPORTER_OTLP_TRACES_CLIENT_CERTIFICATE_STRING` | `OTEL_EXPORTER_OTLP_METRICS_CLIENT_CERTIFICATE_STRING` | `OTEL_EXPORTER_OTLP_LOGS_CLIENT_CERTIFICATE_STRING`
SSL client certificate, as a string.
- `OTEL_R_EXPORTER_OTLP_SSL_MIN_TLS` | `OTEL_R_EXPORTER_OTLP_TRACES_SSL_MIN_TLS` | `OTEL_R_EXPORTER_OTLP_METRICS_SSL_MIN_TLS` | `OTEL_R_EXPORTER_OTLP_LOGS_SSL_MIN_TLS`
Minimum TLS version.
- `OTEL_R_EXPORTER_OTLP_SSL_MAX_TLS` | `OTEL_R_EXPORTER_OTLP_TRACES_SSL_MAX_TLS` | `OTEL_R_EXPORTER_OTLP_METRICS_SSL_MAX_TLS` | `OTEL_R_EXPORTER_OTLP_LOGS_SSL_MAX_TLS`
Maximum TLS version.
- `OTEL_R_EXPORTER_OTLP_SSL_CIPHER` | `OTEL_R_EXPORTER_OTLP_TRACES_SSL_CIPHER` | `OTEL_R_EXPORTER_OTLP_METRICS_SSL_CIPHER` | `OTEL_R_EXPORTER_OTLP_LOGS_SSL_CIPHER`
TLS cipher.
- `OTEL_R_EXPORTER_OTLP_SSL_CIPHER_SUITE` | `OTEL_R_EXPORTER_OTLP_TRACES_SSL_CIPHER_SUITE` | `OTEL_R_EXPORTER_OTLP_METRICS_SSL_CIPHER_SUITE` | `OTEL_R_EXPORTER_OTLP_LOGS_SSL_CIPHER_SUITE`
TLS cipher suite.
- `OTEL_EXPORTER_OTLP_COMPRESSION` | `OTEL_EXPORTER_OTLP_TRACES_COMPRESSION` | `OTEL_EXPORTER_OTLP_METRICS_COMPRESSION` | `OTEL_EXPORTER_OTLP_LOGS_COMPRESSION`
Compression to use. none, gzip.
- `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_MAX_ATTEMPTS` | `OTEL_R_EXPORTER_OTLP_TRACES_RETRY_POLICY_MAX_ATTEMPTS` | `OTEL_R_EXPORTER_OTLP_METRICS_RETRY_POLICY_MAX_ATTEMPTS` | `OTEL_R_EXPORTER_OTLP_LOGS_RETRY_POLICY_MAX_ATTEMPTS`
The maximum number of call attempts, including the original attempt.
- `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_INITIAL_BACKOFF` | `OTEL_R_EXPORTER_OTLP_TRACES_RETRY_POLICY_INITIAL_BACKOFF` | `OTEL_R_EXPORTER_OTLP_METRICS_RETRY_POLICY_INITIAL_BACKOFF` | `OTEL_R_EXPORTER_OTLP_LOGS_RETRY_POLICY_INITIAL_BACKOFF`
The maximum initial back-off delay between retry attempts. The actual backoff delay is uniform random between zero and this. It is in milliseconds.

- OTEL_R_EXPORTER_OTLP_RETRY_POLICY_MAX_BACKOFF | OTEL_R_EXPORTER_OTLP_TRACES_RETRY_POLICY_MAX_BACKOFF | OTEL_R_EXPORTER_OTLP_METRICS_RETRY_POLICY_MAX_BACKOFF | OTEL_R_EXPORTER_OTLP_LOGS_RETRY_POLICY_MAX_BACKOFF
The maximum backoff places an upper limit on exponential backoff growth.
- OTEL_R_EXPORTER_OTLP_RETRY_POLICY_BACKOFF_MULTIPLIER | OTEL_R_EXPORTER_OTLP_TRACES_RETRY_POLICY_BACKOFF_MULTIPLIER | OTEL_R_EXPORTER_OTLP_METRICS_RETRY_POLICY_BACKOFF_MULTIPLIER | OTEL_R_EXPORTER_OTLP_LOGS_RETRY_POLICY_BACKOFF_MULTIPLIER
The backoff will be multiplied by this value after each retry attempt.

OTLP/FILE Exporters

These environment variables are used by [tracer_provider_file](#), [meter_provider_file](#) and [logger_provider_file](#).

For every set of environment variables, the signal specific ones have priority over the generic one.

- OTEL_EXPORTER_OTLP_FILE | OTEL_EXPORTER_OTLP_TRACES_FILE | OTEL_EXPORTER_OTLP_METRICS_FILE | OTEL_EXPORTER_OTLP_LOGS_FILE
Output file pattern. May contain placeholders, see the manual pages of the providers, linked at the beginning of the section.
- OTEL_EXPORTER_OTLP_FILE_ALIAS | OTEL_EXPORTER_OTLP_TRACES_FILE_ALIAS | OTEL_EXPORTER_OTLP_METRICS_FILE_ALIAS | OTEL_EXPORTER_OTLP_LOGS_FILE_ALIAS
The file which always point to the latest file. May contain placeholders, see the manual pages of the providers, linked at the beginning of the section.
- OTEL_EXPORTER_OTLP_FILE_FLUSH_INTERVAL | OTEL_EXPORTER_OTLP_TRACES_FILE_FLUSH_INTERVAL | OTEL_EXPORTER_OTLP_METRICS_FILE_FLUSH_INTERVAL | OTEL_EXPORTER_OTLP_LOGS_FILE_FLUSH_INTERVAL
Interval to force flush output. A time interval specification, see [Time Interval Options](#).
- OTEL_EXPORTER_OTLP_FILE_FLUSH_COUNT | OTEL_EXPORTER_OTLP_TRACES_FILE_FILE_SIZE | OTEL_EXPORTER_OTLP_METRICS_FILE_FILE_SIZE | OTEL_EXPORTER_OTLP_LOGS_FILE_FILE_SIZE
Force flush output after every `flush_count` records.
- OTEL_EXPORTER_OTLP_FILE_FILE_SIZE | OTEL_EXPORTER_OTLP_TRACES_FILE_FILE_SIZE | OTEL_EXPORTER_OTLP_METRICS_FILE_FILE_SIZE | OTEL_EXPORTER_OTLP_LOGS_FILE_FILE_SIZE
File size to rotate output files. A file size specification, see [File Size Options](#).
- OTEL_EXPORTER_OTLP_FILE_ROTATE_SIZE | OTEL_EXPORTER_OTLP_TRACES_FILE_ROTATE_SIZE | OTEL_EXPORTER_OTLP_METRICS_FILE_ROTATE_SIZE | OTEL_EXPORTER_OTLP_LOGS_FILE_ROTATE_SIZE
How many rotated output files to keep.

Batch Processor

These environment variables are used by [tracer_provider_http](#), and [logger_provider_http](#).

- OTEL_BSP_SCHEDULE_DELAY
The maximum buffer/queue size. After the size is reached, spans are dropped. Must be positive.
- OTEL_BSP_MAX_QUEUE_SIZE
The maximum batch size of every export. It must be smaller or equal to `max_queue_size`. Must be positive.
- OTEL_BSP_MAX_EXPORT_BATCH_SIZE
The time interval between two consecutive exports, in milliseconds.

Metric Reader

These environment variables are used by [meter_provider_http](#), [meter_provider_stdstream](#), [meter_provider_memory](#) and [meter_provider_file](#).

- `OTEL_METRIC_EXPORT_INTERVAL`
The time interval between the start of two export attempts, in milliseconds.
- `OTEL_METRIC_EXPORT_TIMEOUT`
Maximum allowed time to export data, in milliseconds.

Metric Exporters

These environment variables are used by [meter_provider_http](#) and [meter_provider_memory](#).

- `OTEL_R_EXPORTER_OTLP_AGGREGATION_TEMPORALITY`
Aggregation temporality. Possible values: unspecified, delta, cumulative, lowmemory. See the [OpenTelemetry data model](#).

Standard Stream Exporters

These environment variables are used by [tracer_provider_stdstream](#), [meter_provider_stdstream](#) and [logger_provider_stdstream](#).

The signal specific environment variables have priority over the generic one.

- `OTEL_R_EXPORTER_STDSTREAM_OUTPUT | OTEL_R_EXPORTER_STDSTREAM_TRACES_OUTPUT | OTEL_R_EXPORTER_STDSTREAM_LOGS_OUTPUT`
Where to write the output. Can be
 - `stdout`: write output to the standard output,
 - `stderr`: write output to the standard error,
 - another string: write output to a file. (To write output to a file named `stdout` or `stderr`, use a `./` prefix.)

In-Memory Exporters

These environment variables are used by [tracer_provider_memory](#) and [meter_provider_memory](#).

The signal specific environment variables have priority over the generic one.

- `OTEL_R_EXPORTER_MEMORY_BUFFER_SIZE | OTEL_R_EXPORTER_MEMORY_TRACES_BUFFER_SIZE | OTEL_R_EXPORTER_MEMORY_METRICS_BUFFER_SIZE`
Buffer size, this is the maximum number of spans or metrics measurements that the provider can record.

Support Matrix of all OpenTelemetry Environment Variables for R

<i>Name</i>	<i>Supported</i>
<code>OTEL_SDK_DISABLED</code>	+
<code>OTEL_RESOURCE_ATTRIBUTES</code>	+
<code>OTEL_SERVICE_NAME</code>	+

OTEL_LOG_LEVEL	+
OTEL_PROPAGATORS	-
OTEL_BSP_SCHEDULE_DELAY	+
OTEL_BSP_EXPORT_TIMEOUT	-
OTEL_BSP_MAX_QUEUE_SIZE	+
OTEL_BSP_MAX_EXPORT_BATCH_SIZE	+
OTEL_EXPORTER_OTLP_ENDPOINT	+
OTEL_EXPORTER_OTLP*_ENDPOINT	+
OTEL_EXPORTER_OTLP_INSECURE	-
OTEL_EXPORTER_OTLP*_INSECURE	-
OTEL_EXPORTER_OTLP_CERTIFICATE	+
OTEL_EXPORTER_OTLP*_CERTIFICATE	+
OTEL_EXPORTER_OTLP_CLIENT_KEY	+
OTEL_EXPORTER_OTLP*_CLIENT_KEY	+
OTEL_EXPORTER_OTLP_CLIENT_CERTIFICATE	+
OTEL_EXPORTER_OTLP_CLIENT*_CERTIFICATE	+
OTEL_EXPORTER_OTLP_HEADERS	+
OTEL_EXPORTER_OTLP*_HEADERS	+
OTEL_EXPORTER_OTLP_COMPRESSION	+
OTEL_EXPORTER_OTLP*_COMPRESSION	+
OTEL_EXPORTER_OTLP_PROTOCOL	+
OTEL_EXPORTER_OTLP*_PROTOCOL	+
OTEL_EXPORTER_OTLP_SPAN_INSECURE (obsolete)	-
OTEL_EXPORTER_OTLP_METRIC_INSECURE (obsolete)	-
OTEL_EXPORTER_ZIPKIN_ENDPOINT	-
OTEL_EXPORTER_ZIPKIN_TIMEOUT	-
OTEL_EXPORTER_PROMETHEUS_HOST	-
OTEL_EXPORTER_PROMETHEUS_PORT	-
OTEL_TRACES_EXPORTER	+
OTEL_METRICS_EXPORTER	+
OTEL_LOGS_EXPORTER	+
OTEL_SPAN_ATTRIBUTE_COUNT_LIMIT	-
OTEL_SPAN_ATTRIBUTE_VALUE_LENGTH_LIMIT	-
OTEL_SPAN_EVENT_COUNT_LIMIT	-
OTEL_SPAN_LINK_COUNT_LIMIT	-
OTEL_EVENT_ATTRIBUTE_COUNT_LIMIT	-
OTEL_LINK_ATTRIBUTE_COUNT_LIMIT	-
OTEL_LOGRECORD_ATTRIBUTE_COUNT_LIMIT	-
OTEL_LOGRECORD_ATTRIBUTE_VALUE_LENGTH_LIMIT	-
OTEL_TRACES_SAMPLER	-
OTEL_TRACES_SAMPLER_ARG	-
OTEL_ATTRIBUTE_VALUE_LENGTH_LIMIT (1)	+
OTEL_ATTRIBUTE_COUNT_LIMIT (1)	+
OTEL_METRIC_EXPORT_INTERVAL	+
OTEL_METRIC_EXPORT_TIMEOUT	+
OTEL_METRICS_EXEMPLAR_FILTER	-
OTEL_EXPORTER_OTLP_METRICS_TEMPORALITY_PREFERENCE	-
OTEL_EXPORTER_OTLP_METRICS_DEFAULT_HISTOGRAM_AGGREGATION	-

OTEL_EXPERIMENTAL_CONFIG_FILE

-

(1) In `otel::as_attributes()`.

See Also

[Environment Variables](#) in `otel`

Examples

```
# To start an R session using the OTLP exporter:
# OTEL_TRACES_EXPORTER=http R -q -f script.R
```

File Size Options *File Size Options*

Description

`otel` and `otelsdk` accept file size options in the following format:

- As a positive numeric scalar, interpreted as number of bytes.
- A string scalar with a positive number and a unit suffix. Possible units: B, KB, KiB, MB, MiB, GB, GiB, TB, TiB, PB, PiB. Units are case insensitive.

Value

Not applicable.

Examples

```
# Maximum output file size is 128 MiB:
# OTEL_EXPORTER_OTLP_FILE_FILE_SIZE=128MiB
```

logger_provider_file *Logger provider to write log messages into a JSONL file.*

Description

This is the **OTLP file exporter**. It writes logs to a JSONL file, each log is a line in the file, a valid JSON value. The line separator is `\n`. The preferred file extension is `jsonl`.

Select this tracer provider with `OTEL_LOGS_EXPORTER=otlp/file`.

Value

logger_provider_file\$new() returns an `otel::otel_logger_provider` object.

logger_provider_file\$options() returns a named list, the current values of the options.

Usage

Externally:

```
OTEL_LOGS_EXPORTER=otlp/file
```

From R:

```
logger_provider_file$new(opts = NULL)
logger_provider_file$options()
```

Arguments

- `opts`: Named list of options. See below.

Options**File exporter options:**

- `file_pattern`: Output file pattern. Value is set from:
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_LOGS_FILE` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE` environment variable, or
 - the default is: `logs-%N.jsonl`.
 May contain placeholders, see below.
- `alias_pattern`: The file which always point to the latest file. Value is set from:
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_LOGS_FILE_ALIAS` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_ALIAS` environment variable, or
 - the default is: `logs-latest.jsonl`.
 May contain placeholders, see below.
- `flush_interval`: Interval to force flush output. A time interval specification, see [Time Interval Options](#). Value is set from
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_LOGS_FILE_FLUSH_INTERVAL` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_FLUSH_INTERVAL` environment variable, or
 - the default is `30s`, thirty seconds.
- `flush_count`: Force flush output after every `flush_count` records. Value is set from
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_LOGS_FILE_FLUSH_COUNT` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_FLUSH_COUNT` environment variable, or

- the default is 256.
- `file_size`: File size to rotate output files. A file size specification, see [File Size Options](#). Value is set from
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_LOGS_FILE_FILE_SIZE` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_FILE_SIZE` environment variable, or
 - the default is 20MB.
- `rotate_size`: How many rotated output files to keep. Value is set from
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_LOGS_FILE_ROTATE_SIZE` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_ROTATE_SIZE` environment variable, or
 - the default is 10.

Special placeholders are available for `file_pattern` and `alias_pattern`:

- `%Y`: Writes year as a 4 digit decimal number.
- `%y`: Writes last 2 digits of year as a decimal number (range [00, 99]).
- `%m`: Writes month as a decimal number (range [01, 12]).
- `%j`: Writes day of the year as a decimal number (range [001, 366]).
- `%d`: Writes day of the month as a decimal number (range [01, 31]).
- `%w`: Writes weekday as a decimal number, where Sunday is 0 (range [0-6]).
- `%H`: Writes hour as a decimal number, 24 hour clock (range [00-23]).
- `%I`: Writes hour as a decimal number, 12 hour clock (range [01, 12]).
- `%M`: Writes minute as a decimal number (range [00, 59]).
- `%S`: Writes second as a decimal number (range [00, 60]).
- `%F`: Equivalent to `%Y-%m-%d` (the ISO 8601 date format).
- `%T`: Equivalent to `%H:%M:%S` (the ISO 8601 time format).
- `%R`: Equivalent to `%H:%M`.
- `%N`: Rotate index, start from 0.
- `%n`: Rotate index, start from 1.

Examples

```
logger_provider_file$options()
```

```
logger_provider_http  Logger provider to log over HTTP
```

Description

This is the OTLP HTTP exporter.

Value

`logger_provider_http$new()` returns an `otel::otel_logger_provider` object.

`logger_provider_http$options()` returns a named list, the current values for all options.

Usage

Externally:

```
OTEL_LOGS_EXPORTER=otlp
```

From R:

```
logger_provider_http$new(opts = NULL)
logger_provider_http$options()
```

Arguments

- `opts`: Named list of options. See below.

Options**HTTP exporter options:**

- `url`: OTLP URL to send telemetry data to. Value is set from
 - the `opts` argument, needs to point to the logs endpoint, or
 - `OTEL_EXPORTER_OTLP_LOGS_ENDPOINT` environment variable, needs to point to the logs endpoint, or
 - `OTEL_EXPORTER_OTLP_ENDPOINT` environment variable + `/v1/logs`, or
 - the default is `http://localhost:4318/v1/logs`.
- `content_type`: data format used, JSON or binary. Possible values: "http/json", "http/protobuf". Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_LOGS_PROTOCOL` environment variable, or
 - the `OTEL_EXPORTER_OTLP_PROTOCOL` environment variable, or
 - the default is "http/protobuf".
- `json_bytes_mapping`: encoding used for trace id and span id. Possible values: "hexid", "base64", "hex". Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_LOGS_JSON_BYTES_MAPPING` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_JSON_BYTES_MAPPING` environment variable, or
 - the default is "hexid".
- `use_json_name`: whether to use json name of protobuf field to set the key of json. A flag. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_LOGS_USE_JSON_NAME` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_USE_JSON_NAME` environment variable, or
 - the default is FALSE.
- `console_debug`: whether to print debug messages to the console. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_LOGS_CONSOLE_DEBUG` environment variable, or

- the OTEL_R_EXPORTER_OTLP_CONSOLE_DEBUG environment variable, or
 - the default is FALSE.
- `timeout`: HTTP timeout in milliseconds. Value is set from
 - the `opts` argument, or
 - the OTEL_EXPORTER_OTLP_LOGS_TIMEOUT} environment variable, or
 - the OTEL_EXPORTER_OTLP_TIMEOUT environment variable, or
 - the default is 10000.
- `http_headers`: additional HTTP headers to send, e.g. Authorization is commonly used. A named character vector without NA values. Value is set from
 - the `opts` argument, or
 - the OTEL_EXPORTER_OTLP_LOGS_HEADERS environment variable, or
 - the OTEL_EXPORTER_OTLP_HEADERS environment variable, or
 - the default is an empty named character vector. When specified in environment variables, it must be a comma separated list of headers, each in the header=value form.
- `ssl_insecure_skip_verify`: whether to disable SSL. Value is set from
 - the `opts` argument, or
 - the OTEL_R_EXPORTER_OTLP_LOGS_SSL_INSECURE_SKIP_VERIFY environment variable, or
 - the OTEL_R_EXPORTER_OTLP_SSL_INSECURE_SKIP_VERIFY environment variable, or
 - the default is FALSE.
- `ssl_ca_cert_path`: CA certificate, path to a file. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the OTEL_EXPORTER_OTLP_LOGS_CERTIFICATE environment variable, or
 - the OTEL_EXPORTER_OTLP_CERTIFICATE environment variable, or
 - the default is “.”
- `ssl_ca_cert_string`: CA certificate, as a string. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the OTEL_EXPORTER_OTLP_LOGS_CERTIFICATE_STRING environment variable, or
 - the OTEL_EXPORTER_OTLP_CERTIFICATE_STRING environment variable, or
 - the default is “.”
- `ssl_client_key_path`: SSL client key, path to a file. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the OTEL_EXPORTER_OTLP_LOGS_CLIENT_KEY environment variable, or
 - the OTEL_EXPORTER_OTLP_CLIENT_KEY environment variable, or
 - the default is “.”
- `ssl_client_key_string`: SSL client key as a string. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the OTEL_EXPORTER_OTLP_LOGS_CLIENT_KEY_STRING environment variable, or
 - the OTEL_EXPORTER_OTLP_CLIENT_KEY_STRING environment variable, or

- the default is “.
- `ssl_client_cert_path`: SSL client certificate, path to a file. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_LOGS_CLIENT_CERTIFICATE` environment variable, or
 - the `OTEL_EXPORTER_OTLP_CLIENT_CERTIFICATE` environment variable, or
 - the default is “.
- `ssl_client_cert_string`: SSL client certificate, as a string. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_LOGS_CLIENT_CERTIFICATE_STRING` environment variable, or
 - the `OTEL_EXPORTER_OTLP_CLIENT_CERTIFICATE_STRING` environment variable, or
 - the default is “.
- `ssl_min_tls`: minimum TLS version. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_LOGS_SSL_MIN_TLS` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_MIN_TLS` environment variable, or
 - the default is “.
- `ssl_max_tls`: maximum TLS version. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_LOGS_SSL_MAX_TLS` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_MAX_TLS` environment variable, or
 - the default is “.
- `ssl_cipher`: TLS cipher. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_LOGS_SSL_CIPHER` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_CIPHER` environment variable, or
 - the default is “.
- `ssl_cipher_suite`: TLS cipher suite. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_LOGS_SSL_CIPHER_SUITE` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_CIPHER_SUITE` environment variable, or
 - the default is “.
- `compression`: compression to use. Possible values are “none”, “gzip”. Value is the set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_LOGS_COMPRESSION` environment variable, or
 - the `OTEL_EXPORTER_OTLP_COMPRESSION` environment variable, or
 - the default is none.

- `retry_policy_max_attempts`: the maximum number of call attempts, including the original attempt. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_LOGS_RETRY_POLICY_MAX_ATTEMPTS` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_MAX_ATTEMPTS` environment variable, or
 - the default is 5.
- `retry_policy_initial_backoff`: the maximum initial back-off delay between retry attempts. The actual backoff delay is uniform random between zero and this. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_LOGS_RETRY_POLICY_INITIAL_BACKOFF` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_INITIAL_BACKOFF` environment variable, or
 - the default is 1000.
- `retry_policy_max_backoff`: the maximum backoff places an upper limit on exponential backoff growth. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_LOGS_RETRY_POLICY_MAX_BACKOFF` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_MAX_BACKOFF` environment variable, or
 - the default is 5000.
- `retry_policy_backoff_multiplier`: the backoff will be multiplied by this value after each retry attempt. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_LOGS_RETRY_POLICY_BACKOFF_MULTIPLIER` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_BACKOFF_MULTIPLIER` environment variable, or
 - the default is 1.5.

Batch processor options:

- `max_queue_size`: The maximum buffer/queue size. After the size is reached, spans are dropped. Must be positive. Value is set from
 - the `opts` argument, or
 - the `OTEL_BSP_MAX_QUEUE_SIZE` environment variable, or
 - the default is 2048.
- `max_export_batch_size`: the maximum batch size of every export. It must be smaller or equal to `max_queue_size`. Must be positive. Value is set from
 - the `opts` argument, or
 - the `OTEL_BSP_MAX_EXPORT_BATCH_SIZE` environment variable, or
 - the default is 512.
- `schedule_delay`: the time interval between two consecutive exports, in milliseconds. Value is set from

- the opts argument⁴ or
- the OTEL_BSP_SCHEDULE_DELAY environment variable, or
- the default is 5000.

Examples

```
logger_provider_http$options()
```

```
logger_provider_stdstream
```

Logger provider to write to the standard output or standard error or to a file

Description

Writes logs to the standard output or error, or to a file. Useful for debugging.

Value

logger_provider_stdstream\$new() returns an [otel::otel_logger_provider](#) object.

logger_provider_stdstream\$options() returns a named list, the current values of the options.

Usage

Externally:

```
OTEL_LOGS_EXPORTER=console
OTEL_LOGS_EXPORTER=stderr
```

From R:

```
logger_provider_stdstream$new(opts = NULL)
logger_provider_stdstream$options()
```

Arguments

opts: Named list of options. See below.

Options

Standard stream exporter options:

- output: where to write the output. Can be
 - "stdout": write output to the standard output,
 - "stderr": write output to the standard error,
 - another string: write output to a file. (To write output to a file named "stdout" or "stderr", use a ./ prefix.)

Value is set from

- the opts argument, or
- the OTEL_R_EXPORTER_STDSTREAM_LOGS_OUTPUT environment variable, or
- the OTEL_R_EXPORTER_STDSTREAM_OUTPUT environment variable, or
- the default is "stdout".

Examples

```
logger_provider_stdstream$options()
```

meter_provider_file *Meter provider to collect metrics in JSONL files*

Description

This is the **OTLP file exporter**. It writes measurements to a JSONL file, each measurement is a line in the file, a valid JSON value. The line separator is `\n`. The preferred file extension is `jsonl`.

Select this tracer provider with `OTEL_METRICS_EXPORTER=otlp/file`.

Value

`meter_provider_file$new()` returns an `otel::otel_meter_provider` object.

`meter_provider_file$options()` returns a named list, the current values of the options.

Usage

Externally:

```
OTEL_METRICS_EXPORTER=otlp/file
```

From R:

```
meter_provider_file$new(opts = NULL)
meter_provider_file$options()
```

Arguments

- `opts`: Named list of options. See below.

Options

File exporter options:

- `file_pattern`: Output file pattern. Value is set from:
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_METRICS_FILE` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE` environment variable, or
 - the default is: `metrics-%N.jsonl`.
 May contain placeholders, see below.
- `alias_pattern`: The file which always point to the latest file. Value is set from:
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_METRICS_FILE_ALIAS` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_ALIAS` environment variable, or
 - the default is: `metrics-latest.jsonl`.
 May contain placeholders, see below.
- `flush_interval`: Interval to force flush output. A time interval specification, see [Time Interval Options](#). Value is set from
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_METRICS_FILE_FLUSH_INTERVAL` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_FLUSH_INTERVAL` environment variable, or
 - the default is `30s`, thirty seconds.
- `flush_count`: Force flush output after every `flush_count` records. Value is set from
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_METRICS_FILE_FLUSH_COUNT` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_FLUSH_COUNT` environment variable, or
 - the default is `256`.
- `file_size`: File size to rotate output files. A file size specification, see [File Size Options](#). Value is set from
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_METRICS_FILE_FILE_SIZE` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_FILE_SIZE` environment variable, or
 - the default is `20MB`.
- `rotate_size`: How many rotated output files to keep. Value is set from
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_METRICS_FILE_ROTATE_SIZE` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_ROTATE_SIZE` environment variable, or
 - the default is `10`.

Special placeholders are available for `file_pattern` and `alias_pattern`:

- `%Y`: Writes year as a 4 digit decimal number.
- `%y`: Writes last 2 digits of year as a decimal number (range `[00, 99]`).
- `%m`: Writes month as a decimal number (range `[01, 12]`).
- `%j`: Writes day of the year as a decimal number (range `[001, 366]`).
- `%d`: Writes day of the month as a decimal number (range `[01, 31]`).

- %w: Writes weekday as a decimal number, where Sunday is 0 (range [0-6]).
- %H: Writes hour as a decimal number, 24 hour clock (range [00-23]).
- %I: Writes hour as a decimal number, 12 hour clock (range [01, 12]).
- %M: Writes minute as a decimal number (range [00, 59]).
- %S: Writes second as a decimal number (range [00, 60]).
- %F: Equivalent to %Y-%m-%d (the ISO 8601 date format).
- %T: Equivalent to %H:%M:%S (the ISO 8601 time format).
- %R: Equivalent to %H:%M.
- %N: Rotate index, start from 0.
- %n: Rotate index, start from 1.

Metric reader options:

- `export_interval`: the time interval between the start of two export attempts, in milliseconds. Value is set from
 - the `opts` argument, or
 - the `OTEL_METRIC_EXPORT_INTERVAL` environment variable, or
 - the default is `60000`.
- `export_timeout`: Maximum allowed time to export data, in milliseconds. Value is set from
 - the `opts` argument, or
 - the `OTEL_METRIC_EXPORT_TIMEOUT` environment variable, or
 - the default is `30000`.

Examples

```
meter_provider_file$options()
```

```
meter_provider_http    Meter provider to send collected metrics over HTTP
```

Description

This is the OTLP HTTP exporter.

Select this tracer provider with `OTEL_METRICS_EXPORTER=otlp`.

Value

`meter_provider_http$new()` returns an `otel::otel_meter_provider` object.

`meter_provider_http$options()` returns a named list, the current values for all options.

Usage

Externally:

```
OTEL_METRICS_EXPORTER=otlp
```

From R:

```
meter_provider_http$new(opts = NULL)
meter_provider_http$options()
```

Arguments

- `opts`: Named list of options. See below.

Options**HTTP exporter options:**

- `url`: OTLP URL to send telemetry data to. Value is set from
 - the `opts` argument, needs to point to the metrics endpoint, or
 - `OTEL_EXPORTER_OTLP_METRICS_ENDPOINT` environment variable, needs to point to the metrics endpoint, or
 - `OTEL_EXPORTER_OTLP_ENDPOINT` environment variable + `/v1/metrics`, or
 - the default is `http://localhost:4318/v1/metrics`.
- `content_type`: data format used, JSON or binary. Possible values: `"http/json"`, `"http/protobuf"`. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_METRICS_PROTOCOL` environment variable, or
 - the `OTEL_EXPORTER_OTLP_PROTOCOL` environment variable, or
 - the default is `"http/protobuf"`.
- `json_bytes_mapping`: encoding used for trace id and span id. Possible values: `"hexid"`, `"base64"`, `"hex"`. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_METRICS_JSON_BYTES_MAPPING` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_JSON_BYTES_MAPPING` environment variable, or
 - the default is `"hexid"`.
- `use_json_name`: whether to use json name of protobuf field to set the key of json. A flag. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_METRICS_USE_JSON_NAME` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_USE_JSON_NAME` environment variable, or
 - the default is `FALSE`.
- `console_debug`: whether to print debug messages to the console. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_METRICS_CONSOLE_DEBUG` environment variable, or

- the OTEL_R_EXPORTER_OTLP_CONSOLE_DEBUG environment variable, or
 - the default is FALSE.
- `timeout`: HTTP timeout in milliseconds. Value is set from
 - the `opts` argument, or
 - the OTEL_EXPORTER_OTLP_METRICS_TIMEOUT environment variable, or
 - the OTEL_EXPORTER_OTLP_TIMEOUT environment variable, or
 - the default is 10000.
- `http_headers`: additional HTTP headers to send, e.g. Authorization is commonly used. A named character vector without NA values. Value is set from
 - the `opts` argument, or
 - the OTEL_EXPORTER_OTLP_METRICS_HEADERS environment variable, or
 - the OTEL_EXPORTER_OTLP_HEADERS environment variable, or
 - the default is an empty named character vector. When specified in environment variables, it must be a comma separated list of headers, each in the header=value form.
- `ssl_insecure_skip_verify`: whether to disable SSL. Value is set from
 - the `opts` argument, or
 - the OTEL_R_EXPORTER_OTLP_METRICS_SSL_INSECURE_SKIP_VERIFY environment variable, or
 - the OTEL_R_EXPORTER_OTLP_SSL_INSECURE_SKIP_VERIFY environment variable, or
 - the default is FALSE.
- `ssl_ca_cert_path`: CA certificate, path to a file. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the OTEL_EXPORTER_OTLP_METRICS_CERTIFICATE environment variable, or
 - the OTEL_EXPORTER_OTLP_CERTIFICATE environment variable, or
 - the default is “”.
- `ssl_ca_cert_string`: CA certificate, as a string. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the OTEL_EXPORTER_OTLP_METRICS_CERTIFICATE_STRING environment variable, or
 - the OTEL_EXPORTER_OTLP_CERTIFICATE_STRING environment variable, or
 - the default is “”.
- `ssl_client_key_path`: SSL client key, path to a file. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the OTEL_EXPORTER_OTLP_METRICS_CLIENT_KEY environment variable, or
 - the OTEL_EXPORTER_OTLP_CLIENT_KEY environment variable, or
 - the default is “”.
- `ssl_client_key_string`: SSL client key as a string. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the OTEL_EXPORTER_OTLP_METRICS_CLIENT_KEY_STRING environment variable, or
 - the OTEL_EXPORTER_OTLP_CLIENT_KEY_STRING environment variable, or

- the default is “.
- `ssl_client_cert_path`: SSL client certificate, path to a file. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_METRICS_CLIENT_CERTIFICATE` environment variable, or
 - the `OTEL_EXPORTER_OTLP_CLIENT_CERTIFICATE` environment variable, or
 - the default is “.
- `ssl_client_cert_string`: SSL client certificate, as a string. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_METRICS_CLIENT_CERTIFICATE_STRING` environment variable, or
 - the `OTEL_EXPORTER_OTLP_CLIENT_CERTIFICATE_STRING` environment variable, or
 - the default is “.
- `ssl_min_tls`: minimum TLS version. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_METRICS_SSL_MIN_TLS` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_MIN_TLS` environment variable, or
 - the default is “.
- `ssl_max_tls`: maximum TLS version. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_METRICS_SSL_MAX_TLS` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_MAX_TLS` environment variable, or
 - the default is “.
- `ssl_cipher`: TLS cipher. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_METRICS_SSL_CIPHER` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_CIPHER` environment variable, or
 - the default is “.
- `ssl_cipher_suite`: TLS cipher suite. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_METRICS_SSL_CIPHER_SUITE` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_CIPHER_SUITE` environment variable, or
 - the default is “.
- `compression`: compression to use. Possible values are “none”, “gzip”. Value is the set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_METRICS_COMPRESSION` environment variable, or
 - the `OTEL_EXPORTER_OTLP_COMPRESSION` environment variable, or
 - the default is none.

- `retry_policy_max_attempts`: the maximum number of call attempts, including the original attempt. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_METRICS_RETRY_POLICY_MAX_ATTEMPTS` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_MAX_ATTEMPTS` environment variable, or
 - the default is 5.
- `retry_policy_initial_backoff`: the maximum initial back-off delay between retry attempts. The actual backoff delay is uniform random between zero and this. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_METRICS_RETRY_POLICY_INITIAL_BACKOFF` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_INITIAL_BACKOFF` environment variable, or
 - the default is 1000.
- `retry_policy_max_backoff`: the maximum backoff places an upper limit on exponential backoff growth. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_METRICS_RETRY_POLICY_MAX_BACKOFF` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_MAX_BACKOFF` environment variable, or
 - the default is 5000.
- `retry_policy_backoff_multiplier`: the backoff will be multiplied by this value after each retry attempt. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_METRICS_RETRY_POLICY_BACKOFF_MULTIPLIER` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_BACKOFF_MULTIPLIER` environment variable, or
 - the default is 1.5.

Metric reader options:

- `export_interval`: the time interval between the start of two export attempts, in milliseconds. Value is set from
 - the `opts` argument, or
 - the `OTEL_METRIC_EXPORT_INTERVAL` environment variable, or
 - the default is 60000.
- `export_timeout`: Maximum allowed time to export data, in milliseconds. Value is set from
 - the `opts` argument, or
 - the `OTEL_METRIC_EXPORT_TIMEOUT` environment variable, or
 - the default is 30000.

Metric exporter options:

- aggregation_temporality: possible values: "unspecified", "delta", "cumulative", "lowmemory". See the [OpenTelemetry data model](#). Value is set from
 - the opts argument, or
 - the OTEL_R_EXPORTER_OTLP_AGGREGATION_TEMPORALITY environment variable, or
 - the default is "cumulative".

Examples

```
meter_provider_http$options()
```

```
meter_provider_memory In-memory meter provider for testing
```

Description

Collects metrics measurements in memory. This is useful for testing your instrumented R package or application.

[with_otel_record\(\)](#) uses this meter provider. Use [with_otel_record\(\)](#) in your tests to record telemetry and check that it is correct.

Value

`meter_provider_memory$new()` returns an `otel::otel_meter_provider` object. `mp$get_metrics()` returns a named list of recorded metrics.

`meter_provider_memory$options()` returns a named list, the current values for all options.

Usage

```
mp <- meter_provider_memory$new(opts = NULL)
mp$get_metrics()
meter_provider_memory$options()
mp$get_metrics() erases the internal buffer of the meter provider.
```

Arguments

- opts: Named list of options. See below.

Options

Memory exporter options:

- buffer_size: buffer size, this is the maximum number of spans or metrics measurements that the provider can record. Must be positive. Value is set from
 - the opts argument, or
 - the OTEL_R_EXPORTER_MEMORY_METRICS_BUFFER_SIZE environment variable, or
 - the OTEL_R_EXPORTER_MEMORY_BUFFER_SIZE environment variable, or
 - the default is 100.

Metric reader options:

- `export_interval`: the time interval between the start of two export attempts, in milliseconds. Value is set from
 - the `opts` argument, or
 - the `OTEL_METRIC_EXPORT_INTERVAL` environment variable, or
 - the default is `60000`.
- `export_timeout`: Maximum allowed time to export data, in milliseconds. Value is set from
 - the `opts` argument, or
 - the `OTEL_METRIC_EXPORT_TIMEOUT` environment variable, or
 - the default is `30000`.

Metric exporter options:

- `aggregation_temporality`: possible values: "unspecified", "delta", "cumulative", "lowmemory". See the [OpenTelemetry data model](#). Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_AGGREGATION_TEMPORALITY` environment variable, or
 - the default is "cumulative".

Examples

```
meter_provider_memory$options()
```

```
meter_provider_stdstream
```

Meter provider to write to the standard output or standard error or to a file

Description

Writes metrics measurements to the standard output or error, or to a file. Useful for debugging.

Value

`meter_provider_stdstream$new()` returns an `otel::otel_meter_provider` object.

`meter_provider_stdstream$options()` returns a named list, the current values of the options.

Usage

Externally:

```
OTEL_METRICS_EXPORTER=console
OTEL_METRICS_EXPORTER=stderr
```

From R:

```
meter_provider_stdstream$new(opts = NULL)
meter_provider_stdstream$options()
```

Arguments

opts: Named list of options. See below.

Options

Standard stream exporter options:

- output: where to write the output. Can be
 - "stdout": write output to the standard output,
 - "stderr": write output to the standard error,
 - another string: write output to a file. (To write output to a file named "stdout" or "stderr", use a ./ prefix.)

Value is set from

- the opts argument, or
- the OTEL_R_EXPORTER_STDSTREAM_METRICS_OUTPUT environment variable, or
- the OTEL_R_EXPORTER_STDSTREAM_OUTPUT environment variable, or
- the default is "stdout".

Metric reader options:

- export_interval: the time interval between the start of two export attempts, in milliseconds. Value is set from
 - the opts argument, or
 - the OTEL_METRIC_EXPORT_INTERVAL environment variable, or
 - the default is 60000.
- export_timeout: Maximum allowed time to export data, in milliseconds. Value is set from
 - the opts argument, or
 - the OTEL_METRIC_EXPORT_TIMEOUT environment variable, or
 - the default is 30000.

Examples

```
meter_provider_stdstream$options()
```

Time Interval Options *Time Interval Options*

Description

otel and otelSdk accept time interval options in the following format:

- A `base::difftime` object.
- A positive numeric scalar, interpreted as number of milliseconds. It may be fractional.
- A string scalar with a positive number and a time unit suffix. Possible time units: us (microseconds), ms (milliseconds), s (seconds), m (minutes), h (hours), d (days).

When the time interval is specified in an environment variable, it may be:

- A positive number, interpreted as number of milliseconds. It may be fractional.
- A positive number with a time unit suffix. Possible time units: us (microseconds), ms (milliseconds), s (seconds), m (minutes), h (hours), d (days).

Value

Not applicable.

Examples

```
# Write pending telemetry data to the output file every 5 seconds:
# OTEL_EXPORTER_OTLP_FILE_FLUSH_INTERVAL=5s
```

tracer_provider_file *Tracer provider to write traces into a JSONL file*

Description

This is the **OTLP file exporter**. It writes spans to a JSONL file, each span is a line in the file, a valid JSON value. The line separator is `\n`. The preferred file extension is `jsonl`.

Select this tracer provider with `OTEL_TRACES_EXPORTER=otlp/file`.

Value

`tracer_provider_file$new()` returns an `otel::otel_tracer_provider` object.

`tracer_provider_file$options()` returns a named list, the current values of the options.

Usage

Externally:

```
OTEL_TRACES_EXPORTER=otlp/file
```

From R:

```
tracer_provider_file$new(opts = NULL)
tracer_provider_file$options()
```

Arguments

- `opts`: Named list of options. See below.

Options

File exporter options:

- `file_pattern`: Output file pattern. Value is set from:
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_TRACES_FILE` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE` environment variable, or
 - the default is: `trace-%N.jsonl`.
 May contain placeholders, see below.
- `alias_pattern`: The file which always point to the latest file. Value is set from:
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_TRACES_FILE_ALIAS` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_ALIAS` environment variable, or
 - the default is: `trace-latest.jsonl`.
 May contain placeholders, see below.
- `flush_interval`: Interval to force flush output. A time interval specification, see [Time Interval Options](#). Value is set from
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_TRACES_FILE_FLUSH_INTERVAL` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_FLUSH_INTERVAL` environment variable, or
 - the default is `30s`, thirty seconds.
- `flush_count`: Force flush output after every `flush_count` records. Value is set from
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_TRACES_FILE_FLUSH_COUNT` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_FLUSH_COUNT` environment variable, or
 - the default is `256`.
- `file_size`: File size to rotate output files. A file size specification, see [File Size Options](#). Value is set from
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_TRACES_FILE_FILE_SIZE` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_FILE_SIZE` environment variable, or
 - the default is `20MB`.
- `rotate_size`: How many rotated output files to keep. Value is set from
 - `opts` argument, or
 - `OTEL_EXPORTER_OTLP_TRACES_FILE_ROTATE_SIZE` environment variable, or
 - `OTEL_EXPORTER_OTLP_FILE_ROTATE_SIZE` environment variable, or
 - the default is `10`.

Special placeholders are available for `file_pattern` and `alias_pattern`:

- `%Y`: Writes year as a 4 digit decimal number.
- `%y`: Writes last 2 digits of year as a decimal number (range `[00, 99]`).
- `%m`: Writes month as a decimal number (range `[01, 12]`).
- `%j`: Writes day of the year as a decimal number (range `[001, 366]`).
- `%d`: Writes day of the month as a decimal number (range `[01, 31]`).

- %w: Writes weekday as a decimal number, where Sunday is 0 (range [0-6]).
- %H: Writes hour as a decimal number, 24 hour clock (range [00-23]).
- %I: Writes hour as a decimal number, 12 hour clock (range [01, 12]).
- %M: Writes minute as a decimal number (range [00, 59]).
- %S: Writes second as a decimal number (range [00, 60]).
- %F: Equivalent to %Y-%m-%d (the ISO 8601 date format).
- %T: Equivalent to %H:%M:%S (the ISO 8601 time format).
- %R: Equivalent to %H:%M.
- %N: Rotate index, start from 0.
- %n: Rotate index, start from 1.

Examples

```
tracer_provider_file$options()
```

```
tracer_provider_http  Tracer provider to export traces over HTTP
```

Description

This is the OTLP HTTP exporter.

Select this tracer provider with `OTEL_TRACES_EXPORTER=otlp`.

Value

`tracer_provider_http$new()` returns an `otel::otel_tracer_provider` object.

`tracer_provider_http$options()` returns a named list, the current values for all options.

Usage

Externally:

```
OTEL_TRACES_EXPORTER=otlp
```

From R:

```
tracer_provider_http$new(opts = NULL)
tracer_provider_http$options()
```

Arguments

- `opts`: Named list of options. See below.

Options

HTTP exporter options:

- `url`: OTLP URL to send telemetry data to. Value is set from
 - the `opts` argument, needs to point to the traces endpoint, or
 - `OTEL_EXPORTER_OTLP_TRACES_ENDPOINT` environment variable, needs to point to the traces endpoint, or
 - `OTEL_EXPORTER_OTLP_ENDPOINT` environment variable + `/v1/traces`, or
 - the default is `http://localhost:4318/v1/traces`.
- `content_type`: data format used, JSON or binary. Possible values: `"http/json"`, `"http/protobuf"`. Value if set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_TRACES_PROTOCOL` environment variable, or
 - the `OTEL_EXPORTER_OTLP_PROTOCOL` environment variable, or
 - the default is `"http/protobuf"`.
- `json_bytes_mapping`: encoding used for trace id and span id. Possible values: `"hexid"`, `"base64"`, `"hex"`. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_TRACES_JSON_BYTES_MAPPING` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_JSON_BYTES_MAPPING` environment variable, or
 - the default is `"hexid"`.
- `use_json_name`: whether to use json name of protobuf field to set the key of json. A flag. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_TRACES_USE_JSON_NAME` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_USE_JSON_NAME` environment variable, or
 - the default is `FALSE`.
- `console_debug`: whether to print debug messages to the console. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_TRACES_CONSOLE_DEBUG` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_CONSOLE_DEBUG` environment variable, or
 - the default is `FALSE`.
- `timeout`: HTTP timeout in milliseconds. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_TRACES_TIMEOUT` environment variable, or
 - the `OTEL_EXPORTER_OTLP_TIMEOUT` environment variable, or
 - the default is `10000`.
- `http_headers`: additional HTTP headers to send, e.g. Authorization is commonly used. A named character vector without NA values. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_TRACES_HEADERS` environment variable, or
 - the `OTEL_EXPORTER_OTLP_HEADERS` environment variable, or
 - the default is an empty named character vector. When specified in environment variables, it must be a comma separated list of headers, each in the `header=value` form.

- `ssl_insecure_skip_verify`: whether to disable SSL. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_TRACES_SSL_INSECURE_SKIP_VERIFY` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_INSECURE_SKIP_VERIFY` environment variable, or
 - the default is `FALSE`.
- `ssl_ca_cert_path`: CA certificate, path to a file. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_TRACES_CERTIFICATE` environment variable, or
 - the `OTEL_EXPORTER_OTLP_CERTIFICATE` environment variable, or
 - the default is `“`.
- `ssl_ca_cert_string`: CA certificate, as a string. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_TRACES_CERTIFICATE_STRING` environment variable, or
 - the `OTEL_EXPORTER_OTLP_CERTIFICATE_STRING` environment variable, or
 - the default is `“`.
- `ssl_client_key_path`: SSL client key, path to a file. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_TRACES_CLIENT_KEY` environment variable, or
 - the `OTEL_EXPORTER_OTLP_CLIENT_KEY` environment variable, or
 - the default is `“`.
- `ssl_client_key_string`: SSL client key as a string. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_TRACES_CLIENT_KEY_STRING` environment variable, or
 - the `OTEL_EXPORTER_OTLP_CLIENT_KEY_STRING` environment variable, or
 - the default is `“`.
- `ssl_client_cert_path`: SSL client certificate, path to a file. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_TRACES_CLIENT_CERTIFICATE` environment variable, or
 - the `OTEL_EXPORTER_OTLP_CLIENT_CERTIFICATE` environment variable, or
 - the default is `“`.
- `ssl_client_cert_string`: SSL client certificate, as a string. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_TRACES_CLIENT_CERTIFICATE_STRING` environment variable, or
 - the `OTEL_EXPORTER_OTLP_CLIENT_CERTIFICATE_STRING` environment variable, or
 - the default is `“`.

- `ssl_min_tls`: minimum TLS version. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_TRACES_SSL_MIN_TLS` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_MIN_TLS` environment variable, or
 - the default is “.”
- `ssl_max_tls`: maximum TLS version. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_TRACES_SSL_MAX_TLS` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_MAX_TLS` environment variable, or
 - the default is “.”
- `ssl_cipher`: TLS cipher. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_TRACES_SSL_CIPHER` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_CIPHER` environment variable, or
 - the default is “.”
- `ssl_cipher_suite`: TLS cipher suite. Empty string uses the system default. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_TRACES_SSL_CIPHER_SUITE` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_SSL_CIPHER_SUITE` environment variable, or
 - the default is “.”
- `compression`: compression to use. Possible values are “none”, “gzip”. Value is the set from
 - the `opts` argument, or
 - the `OTEL_EXPORTER_OTLP_TRACES_COMPRESSION` environment variable, or
 - the `OTEL_EXPORTER_OTLP_COMPRESSION` environment variable, or
 - the default is none.
- `retry_policy_max_attempts`: the maximum number of call attempts, including the original attempt. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_TRACES_RETRY_POLICY_MAX_ATTEMPTS` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_MAX_ATTEMPTS` environment variable, or
 - the default is 5.
- `retry_policy_initial_backoff`: the maximum initial back-off delay between retry attempts. The actual backoff delay is uniform random between zero and this. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_TRACES_RETRY_POLICY_INITIAL_BACKOFF` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_INITIAL_BACKOFF` environment variable, or
 - the default is 5.

- the default is 1000.
- `retry_policy_max_backoff`: the maximum backoff places an upper limit on exponential backoff growth. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_TRACES_RETRY_POLICY_MAX_BACKOFF` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_MAX_BACKOFF` environment variable, or
 - the default is 5000.
- `retry_policy_backoff_multiplier`: the backoff will be multiplied by this value after each retry attempt. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_OTLP_TRACES_RETRY_POLICY_BACKOFF_MULTIPLIER` environment variable, or
 - the `OTEL_R_EXPORTER_OTLP_RETRY_POLICY_BACKOFF_MULTIPLIER` environment variable, or
 - the default is 1.5.

Batch processor options:

- `max_queue_size`: The maximum buffer/queue size. After the size is reached, spans are dropped. Must be positive. Value is set from
 - the `opts` argument, or
 - the `OTEL_BSP_MAX_QUEUE_SIZE` environment variable, or
 - the default is 2048.
- `max_export_batch_size`: the maximum batch size of every export. It must be smaller or equal to `max_queue_size`. Must be positive. Value is set from
 - the `opts` argument, or
 - the `OTEL_BSP_MAX_EXPORT_BATCH_SIZE` environment variable, or
 - the default is 512.
- `schedule_delay`: the time interval between two consecutive exports, in milliseconds. Value is set from
 - the `opts` argument, or
 - the `OTEL_BSP_SCHEDULE_DELAY` environment variable, or
 - the default is 5000.

Examples

```
tracer_provider_http$options()
```

`tracer_provider_memory`*In-memory tracer provider for testing*

Description

Collects spans in memory. This is useful for testing your instrumented R package or application.

`with_otel_record()` uses this tracer provider. Use `with_otel_record()` in your tests to record telemetry and check that it is correct.

Value

`tracer_provider_memory$new()` returns an `otel::otel_tracer_provider` object. `tp$get_spans()` returns a named list of recorded spans, with the span names as names.

`tracer_provider_memory$options()` returns a named list, the current values for all options.

Usage

```
tp <- tracer_provider_memory$new(opts = NULL)
tp$get_spans()
tracer_provider_memory$options()

tp$get_spans() erases the internal buffer of the tracer provider.
```

Arguments

- `opts`: Named list of options. See below.

Options

Memory exporter options:

- `buffer_size`: buffer size, this is the maximum number of spans or metrics measurements that the provider can record. Must be positive. Value is set from
 - the `opts` argument, or
 - the `OTEL_R_EXPORTER_MEMORY_TRACES_BUFFER_SIZE` environment variable, or
 - the `OTEL_R_EXPORTER_MEMORY_BUFFER_SIZE` environment variable, or
 - the default is 100.

Examples

```
tracer_provider_memory$options()
```

tracer_provider_stdstream

Tracer provider to write to the standard output or standard error or to a file

Description

Writes spans to the standard output or error, or to a file. Useful for debugging.

Value

tracer_provider_stdstream\$new() returns an `otel::otel_tracer_provider` object.

tracer_provider_stdstream\$options() returns a named list, the current values of the options.

Usage

Externally:

```
OTEL_TRACES_EXPORTER=console
OTEL_TRACES_EXPORTER=stderr
```

From R:

```
tracer_provider_stdstream$new(opts = NULL)
tracer_provider_stdstream$options()
```

Arguments

opts: Named list of options. See below.

Options

Standard stream exporter options:

- output: where to write the output. Can be
 - "stdout": write output to the standard output,
 - "stderr": write output to the standard error,
 - another string: write output to a file. (To write output to a file named "stdout" or "stderr", use a ./ prefix.)

Value is set from

- the opts argument, or
- the OTEL_R_EXPORTER_STDSTREAM_TRACES_OUTPUT environment variable, or
- the OTEL_R_EXPORTER_STDSTREAM_OUTPUT environment variable, or
- the default is "stdout".

Examples

```
tracer_provider_stdstream$options()
```

with_otel_record	<i>Record OpenTelemetry output, for testing purposes</i>
------------------	--

Description

You can use this function to test that OpenTelemetry output is correctly generated for your package or application.

Usage

```
with_otel_record(  
  expr,  
  what = c("traces", "metrics"),  
  tracer_opts = list(),  
  meter_opts = list()  
)
```

Arguments

expr	Expression to evaluate.
what	Character vector, type(s) of OpenTelemetry output to collect.
tracer_opts	Named list of options to pass to the tracer provider.
meter_opts	Named list of options to pass to the meter provider.

Details

It evaluates the supplied expression, collects OpenTelemetry output from it and returns it.

Note: `with_otel_record()` cannot record logs yet.

`with_otel_record()` uses [tracer_provider_memory](#) and [meter_provider_memory](#) internally.

Value

A list with the output for each output type. Entries:

- value: value of expr.
- traces: the recorded spans, if requested in what.
- metrics: the recorded metrics measurements, if requested in what.

Examples

```
spns <- with_otel_record({  
  trc <- otel::get_tracer("mytracer")  
  spn1 <- trc$start_local_active_span()  
  spn2 <- trc$start_local_active_span("my")  
  spn2$end()  
  spn1$end()  
})
```

```
    NULL  
  })  
spns
```

Index

* datasets

- logger_provider_file, [12](#)
- logger_provider_http, [14](#)
- logger_provider_stdstream, [19](#)
- meter_provider_file, [20](#)
- meter_provider_http, [22](#)
- meter_provider_memory, [27](#)
- meter_provider_stdstream, [28](#)
- tracer_provider_file, [30](#)
- tracer_provider_http, [32](#)
- tracer_provider_memory, [37](#)
- tracer_provider_stdstream, [38](#)

base::difftime, [29](#)

collecting (Collecting Telemetry Data), [2](#)

Collecting Telemetry Data, [2](#)

Environment Variables, [5](#), [5](#), [12](#)

environment variables, [3](#)

File Size Options, [9](#), [12](#), [14](#), [21](#), [31](#)

Getting Started, [2](#)

logger_provider_file, [9](#), [12](#)

logger_provider_http, [7](#), [9](#), [14](#)

logger_provider_stdstream, [10](#), [19](#)

meter_provider_file, [9](#), [10](#), [20](#)

meter_provider_http, [7](#), [10](#), [22](#)

meter_provider_memory, [10](#), [27](#), [39](#)

meter_provider_stdstream, [10](#), [28](#)

otel::as_attributes(), [7](#), [12](#)

otel::default_tracer_name(), [6](#)

otel::get_default_logger_provider(), [5](#)

otel::get_default_meter_provider(), [6](#)

otel::get_default_tracer_provider(), [5](#)

otel::otel_logger_provider, [13](#), [14](#), [19](#)

otel::otel_meter_provider, [20](#), [22](#), [27](#), [28](#)

otel::otel_tracer_provider, [30](#), [32](#), [37](#), [38](#)

OTEL_BSP_MAX_EXPORT_BATCH_SIZE (Environment Variables), [5](#)

OTEL_BSP_MAX_QUEUE_SIZE (Environment Variables), [5](#)

OTEL_BSP_SCHEDULE_DELAY (Environment Variables), [5](#)

OTEL_ENV (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_CERTIFICATE (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_CERTIFICATE_STRING (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_CLIENT_CERTIFICATE (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_CLIENT_CERTIFICATE_STRING (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_CLIENT_KEY (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_CLIENT_KEY_STRING (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_COMPRESSION (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_FILE (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_FILE_ALIAS (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_FILE_FILE_SIZE (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_FILE_FLUSH_COUNT (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_FILE_FLUSH_INTERVAL (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_FILE_ROTATE_SIZE (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_HEADERS (Environment Variables), [5](#)

OTEL_EXPORTER_OTLP_LOGS_CERTIFICATE

- (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_CERTIFICATE_STRING (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_CLIENT_CERTIFICATE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_CLIENT_CERTIFICATE_STRING (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_CLIENT_KEY (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_CLIENT_KEY_STRING (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_COMPRESSION (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_FILE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_FILE_ALIAS (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_FILE_FILE_SIZE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_FILE_FLUSH_INTERVAL (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_FILE_ROTATE_SIZE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_HEADERS (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_PROTOCOL (Environment Variables), 5
- OTEL_EXPORTER_OTLP_LOGS_TIMEOUT (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_CERTIFICATE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_CERTIFICATE_STRING (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_CLIENT_CERTIFICATE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_CLIENT_CERTIFICATE_STRING (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_CLIENT_KEY (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_CLIENT_KEY_STRING (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_COMPRESSION (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_FILE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_FILE_ALIAS (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_FILE_FILE_SIZE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_FILE_FLUSH_INTERVAL (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_FILE_ROTATE_SIZE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_HEADERS (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_PROTOCOL (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_TIMEOUT (Environment Variables), 5
- OTEL_LOG_LEVEL (Environment Variables), 5
- OTEL_LOGS_EXPORTER (Environment
- (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_FILE_FLUSH_INTERVAL (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_FILE_ROTATE_SIZE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_HEADERS (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_PROTOCOL (Environment Variables), 5
- OTEL_EXPORTER_OTLP_METRICS_TIMEOUT (Environment Variables), 5
- OTEL_EXPORTER_OTLP_PROTOCOL (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TIMEOUT (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_CERTIFICATE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_CERTIFICATE_STRING (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_CLIENT_CERTIFICATE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_CLIENT_CERTIFICATE_STRING (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_CLIENT_KEY (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_CLIENT_KEY_STRING (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_COMPRESSION (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_FILE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_FILE_ALIAS (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_FILE_FILE_SIZE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_FILE_FLUSH_INTERVAL (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_FILE_ROTATE_SIZE (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_HEADERS (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_PROTOCOL (Environment Variables), 5
- OTEL_EXPORTER_OTLP_TRACES_TIMEOUT (Environment Variables), 5

(Environment Variables), [5](#)
OTEL_R_EXPORTER_OTLP_TRACES_SSL_MAX_TLS
(Environment Variables), [5](#)
OTEL_R_EXPORTER_OTLP_TRACES_SSL_MIN_TLS
(Environment Variables), [5](#)
OTEL_R_EXPORTER_OTLP_TRACES_USE_JSON_NAME
(Environment Variables), [5](#)
OTEL_R_EXPORTER_OTLP_USE_JSON_NAME
(Environment Variables), [5](#)
OTEL_R_EXPORTER_STDSTREAM_LOGS_OUTPUT
(Environment Variables), [5](#)
OTEL_R_EXPORTER_STDSTREAM_METRICS_OUTPUT
(Environment Variables), [5](#)
OTEL_R_EXPORTER_STDSTREAM_OUTPUT
(Environment Variables), [5](#)
OTEL_R_EXPORTER_STDSTREAM_TRACES_OUTPUT
(Environment Variables), [5](#)
OTEL_R_LOGS_EXPORTER (Environment
Variables), [5](#)
OTEL_R_METRICS_EXPORTER (Environment
Variables), [5](#)
OTEL_R_SUPPRESS_SCOPES (Environment
Variables), [5](#)
OTEL_R_TRACES_EXPORTER (Environment
Variables), [5](#)
OTEL_RESOURCE_ATTRIBUTES (Environment
Variables), [5](#)
OTEL_SDK_DISABLED (Environment
Variables), [5](#)
OTEL_SERVICE_NAME (Environment
Variables), [5](#)
OTEL_TRACES_EXPORTER (Environment
Variables), [5](#)

Time Interval Options, [9](#), [13](#), [21](#), [29](#), [31](#)
tracer_provider_file, [9](#), [30](#)
tracer_provider_http, [7](#), [9](#), [32](#)
tracer_provider_memory, [10](#), [37](#), [39](#)
tracer_provider_stdstream, [10](#), [38](#)

with_otel_record, [39](#)
with_otel_record(), [27](#), [37](#)

Zero Code Instrumentation, [2](#), [6](#)